



# Scalable solvers for the 3D non-Newtonian Stokes problem in ice flow modeling

Jed Brown

VAW, ETH Zürich

CCSM 2009

# Why do we need 3D Stokes?



## Non-Newtonian Stokes system

- Strong form: Find  $(\mathbf{u}, p) \in \mathcal{V}_D \times \mathcal{P}$  such that

$$\begin{aligned} -\nabla \cdot (\eta D\mathbf{u}) + \nabla p - \mathbf{f} &= 0 \\ \nabla \cdot \mathbf{u} &= 0 \end{aligned}$$

where

$$\begin{aligned} D\mathbf{u} &= \frac{1}{2} (\nabla \mathbf{u} + (\nabla \mathbf{u})^T) \\ \gamma(D\mathbf{u}) &= \frac{1}{2} D\mathbf{u} : D\mathbf{u} \\ \eta(\gamma) &= B(\Theta, \dots) (\epsilon + \gamma)^{\frac{p-2}{2}}, \quad p = 1 + \frac{1}{n} \approx \frac{4}{3} \end{aligned}$$

with boundary conditions

$$\begin{aligned} (D\mathbf{u} - p\mathbf{1}) \cdot \mathbf{n} &= \begin{cases} \mathbf{0} & \text{free surface} \\ -\rho_w z \mathbf{n} & \text{ice-ocean interface} \end{cases} \\ \mathbf{u} &= \mathbf{0} & \text{frozen bed, } \Theta < \Theta_0 \\ \left. \begin{aligned} \mathbf{u} \cdot \mathbf{n} &= \mathbf{g}_{\text{melt}}(T\mathbf{u}, \dots) \\ T(D\mathbf{u} - p\mathbf{1}) \cdot \mathbf{n} &= \mathbf{g}_{\text{slip}}(T\mathbf{u}, \dots) \end{aligned} \right\} \text{nonlinear slip, } \Theta \geq \Theta_0 \end{aligned}$$

## Other forms

- ▶ Minimization form: Find  $\mathbf{u} \in \mathcal{V}_D$  which minimizes

$$\mathcal{I}(\mathbf{u}) = \int_{\Omega} |D\mathbf{u}|^p - \mathbf{f} \cdot \mathbf{u}$$

subject to

$$\nabla \cdot \mathbf{u} = 0$$

- ▶ Weak form: Find  $(\mathbf{u}, p) \in \mathcal{V}_D \times \mathcal{P}$  such that

$$\begin{aligned} \int_{\Omega} \eta D\mathbf{v} : D\mathbf{u} - p \nabla \cdot \mathbf{v} - q \nabla \cdot \mathbf{u} - \mathbf{f} \cdot \mathbf{v} \\ - \int_{\partial\Omega} \mathbf{g}(T\mathbf{u}) \cdot \mathbf{v} = 0 \quad \forall (\mathbf{v}, q) \in \mathcal{V}_0 \times \mathcal{P} \end{aligned}$$

- ▶ Slip

$$\mathbf{g}_{\text{slip}}(T\mathbf{u}) = \beta_m(\dots) |T\mathbf{u}|^{m-1} T\mathbf{u}$$

Navier  $m = 1$ , Weertman  $m \approx \frac{1}{3}$ , Coulomb  $m = 0$ .

# Newton iteration


- ▶ Standard form of a nonlinear system

$$F(x) = 0$$

- ▶ Iteration

$$\text{Solve: } J(x^n)s^n = -F(x^n)$$

$$\text{Update: } x^{n+1} \leftarrow x^n + s^n$$



## Stokes problem

$$F(\mathbf{u}, p) \sim \int_{\Omega} \eta D\mathbf{v} : D\mathbf{u} - p \nabla \cdot \mathbf{v} - q \nabla \cdot \mathbf{u} - \mathbf{f} \cdot \mathbf{v} = 0 \quad \forall (\mathbf{v}, q)$$

$$J(\mathbf{w}) \begin{bmatrix} \mathbf{u} \\ p \end{bmatrix} \sim \int_{\Omega} \eta D\mathbf{v} : D\mathbf{u} + \eta' (D\mathbf{v} : D\mathbf{w})(D\mathbf{w} : D\mathbf{u}) \\ - p \nabla \cdot \mathbf{v} - q \nabla \cdot \mathbf{u}$$

$$J(\mathbf{w}) = \begin{bmatrix} A(\mathbf{w}) & B^T \\ B & \end{bmatrix}$$

# Matrices and Preconditioners



## Definition (Matrix)

A **matrix** is a linear transformation between finite dimensional vector spaces.

## Definition (Forming a matrix)

Forming or assembling a matrix means defining it's action in terms of entries (usually stored in a sparse format).

## Definition (Preconditioner)

A preconditioner  $\mathcal{P}$  is a method for constructing a matrix (just a linear function, not assembled!)  $P^{-1} = \mathcal{P}(\hat{J})$  using information  $\hat{J}$ , such that  $P^{-1}J$  (or  $JP^{-1}$ ) has favorable spectral properties.

## Left preconditioning in a Krylov iteration

$$(P^{-1}J)x = P^{-1}b$$
$$\{P^{-1}b, (P^{-1}J)P^{-1}b, (P^{-1}J)^2P^{-1}b, \dots\}$$

# Matrices and Preconditioners

## Definition (Matrix)

A matrix is a linear transformation between finite dimensional vector spaces.

## Definition (Forming a matrix)

**Forming** or **assembling** a matrix means defining it's action in terms of entries (usually stored in a sparse format).

## Definition (Preconditioner)

A preconditioner  $\mathcal{P}$  is a method for constructing a matrix (just a linear function, not assembled!)  $P^{-1} = \mathcal{P}(\hat{J})$  using information  $\hat{J}$ , such that  $P^{-1}J$  (or  $JP^{-1}$ ) has favorable spectral properties.

## Left preconditioning in a Krylov iteration

$$(P^{-1}J)x = P^{-1}b$$
$$\{P^{-1}b, (P^{-1}J)P^{-1}b, (P^{-1}J)^2P^{-1}b, \dots\}$$



# Matrices and Preconditioners



## Definition (Matrix)

A matrix is a linear transformation between finite dimensional vector spaces.

## Definition (Forming a matrix)

Forming or assembling a matrix means defining it's action in terms of entries (usually stored in a sparse format).

## Definition (Preconditioner)


A **preconditioner**  $\mathcal{P}$  is a method for constructing a matrix (just a linear function, not assembled!)  $P^{-1} = \mathcal{P}(\hat{J})$  using information  $\hat{J}$ , such that  $P^{-1}J$  (or  $JP^{-1}$ ) has favorable spectral properties.

## Left preconditioning in a Krylov iteration

$$(P^{-1}J)x = P^{-1}b$$
$$\{P^{-1}b, (P^{-1}J)P^{-1}b, (P^{-1}J)^2P^{-1}b, \dots\}$$



# Matrices and Preconditioners



## Definition (Matrix)

A matrix is a linear transformation between finite dimensional vector spaces.

## Definition (Forming a matrix)

Forming or assembling a matrix means defining it's action in terms of entries (usually stored in a sparse format).


## Definition (Preconditioner)

A preconditioner  $\mathcal{P}$  is a method for constructing a matrix (just a linear function, not assembled!)  $P^{-1} = \mathcal{P}(\hat{J})$  using information  $\hat{J}$ , such that  $P^{-1}J$  (or  $JP^{-1}$ ) has favorable spectral properties.

## Left preconditioning in a Krylov iteration

$$(P^{-1}J)x = P^{-1}b$$
$$\{P^{-1}b, (P^{-1}J)P^{-1}b, (P^{-1}J)^2P^{-1}b, \dots\}$$

# Normal preconditioners fail for indefinite problems



# Stokes

## Weak form of the Newton step

Find  $(\mathbf{u}, p)$  such that

$$\int_{\Omega} \eta D\mathbf{v} : D\mathbf{u} + \eta'(D\mathbf{v} : D\mathbf{w})(D\mathbf{w} : D\mathbf{u}) - p \nabla \cdot \mathbf{v} - q \nabla \cdot \mathbf{u} = -v \cdot F(\mathbf{w}) \quad \forall (\mathbf{v}, q)$$

Matrix

$$\begin{bmatrix} A(\mathbf{w}) & B^T \\ B & \end{bmatrix} \begin{pmatrix} u \\ p \end{pmatrix} = - \begin{pmatrix} F_u(\mathbf{w}) \\ 0 \end{pmatrix}$$

Block factorization

$$\begin{bmatrix} A & B^T \\ B & \end{bmatrix} = \begin{bmatrix} 1 & \\ BA^{-1} & 1 \end{bmatrix} \begin{bmatrix} A & B^T \\ & S \end{bmatrix} = \begin{bmatrix} A & \\ B & S \end{bmatrix} \begin{bmatrix} 1 & A^{-1}B^T \\ & 1 \end{bmatrix}$$

where the Schur complement is

$$S = -BA^{-1}B^T.$$

# Properties of the Schur complement

## Block factorization

$$\begin{bmatrix} A & B^T \\ B & \end{bmatrix} = \begin{bmatrix} 1 & \\ BA^{-1} & 1 \end{bmatrix} \begin{bmatrix} A & B^T \\ & S \end{bmatrix} = \begin{bmatrix} A & \\ B & S \end{bmatrix} \begin{bmatrix} 1 & A^{-1}B^T \\ & 1 \end{bmatrix}$$

where

$$S = -BA^{-1}B^T.$$

- ▶  $S$  is symmetric negative definite if  $A$  is SPD and  $B$  has full rank (discrete inf-sup condition)
- ▶  $S$  is dense
- ▶ We only need to multiply  $B, B^T$  with vectors.
- ▶ We need preconditioners for  $A$  and  $S$ .
- ▶ Any definite preconditioner can be used for  $A$ .
- ▶ It's not obvious how to precondition  $S$ , more on that later.

## Reduced factorizations are sufficient

### Theorem (GMRES convergence)

GMRES applied to

$$Kx = b$$

converges in  $n$  steps for all right hand sides if the minimal polynomial of  $K$  has degree  $n$ .

(There exists a polynomial  $\pi_n$  such that  $\pi_n(K) = 0$  and  $\pi_n(0) = 1$ .)

### A lower-triangular preconditioner

Left precondition  $J$ :

$$\begin{aligned} K = P^{-1}J &= \begin{bmatrix} A & \\ B & S \end{bmatrix}^{-1} \begin{bmatrix} A & B^T \\ B & \end{bmatrix} \\ &= \begin{bmatrix} A^{-1} & \\ -S^{-1}BA^{-1} & S^{-1} \end{bmatrix} \begin{bmatrix} A & B^T \\ B & \end{bmatrix} = \begin{bmatrix} 1 & A^{-1}B^T \\ & 1 \end{bmatrix} \end{aligned}$$

Since  $(K - 1)^2 = 0$ , GMRES converges in at most 2 steps.

## Reduced factorizations are sufficient

### Theorem (GMRES convergence)

GMRES applied to

$$Kx = b$$

converges in  $n$  steps for all right hand sides if the minimal polynomial of  $K$  has degree  $n$ .

(There exists a polynomial  $\pi_n$  such that  $\pi_n(K) = 0$  and  $\pi_n(0) = 1$ .)

### A lower-triangular preconditioner

Left precondition  $J$ :

$$\begin{aligned} K = P^{-1}J &= \begin{bmatrix} A & \\ B & S \end{bmatrix}^{-1} \begin{bmatrix} A & B^T \\ B & \end{bmatrix} \\ &= \begin{bmatrix} A^{-1} & \\ -S^{-1}BA^{-1} & S^{-1} \end{bmatrix} \begin{bmatrix} A & B^T \\ B & \end{bmatrix} = \begin{bmatrix} 1 & A^{-1}B^T \\ & 1 \end{bmatrix} \end{aligned}$$

Since  $(K - 1)^2 = 0$ , GMRES converges in at most 2 steps.

## Preserving symmetry for MINRES

$P$  must be SPD

$$P^{-1} = \begin{bmatrix} A & \\ & -S \end{bmatrix}^{-1}$$
$$K = P^{-1}J = \begin{bmatrix} A^{-1} & \\ & -S^{-1} \end{bmatrix} \begin{bmatrix} A & B^T \\ B & \end{bmatrix} = \begin{bmatrix} 1 & A^{-1}B^T \\ -S^{-1}B & \end{bmatrix}$$
$$\left(K - \frac{1}{2}\right)^2 = \begin{bmatrix} \frac{1}{4} - A^{-1}B^T S^{-1}B & \\ & \frac{5}{4} \end{bmatrix}$$
$$\left(K - \frac{1}{2}\right)^2 - \frac{1}{4} = \begin{bmatrix} -A^{-1}B^T S^{-1}B & \\ & 1 \end{bmatrix}$$

Now  $Q = -A^{-1}B^T S^{-1}B$  is a projector ( $Q^2 = Q$ ) so

$$\left[\left(K - \frac{1}{2}\right)^2 - \frac{1}{4}\right]^2 = \left(K - \frac{1}{2}\right)^2 - \frac{1}{4}$$

Rearranging,  $K(K-1)(K^2-K-1) = 0$ . MINRES converges in at most 3 iterations.

## Preconditioning the Schur complement

- ▶  $S = -BA^{-1}B^T$  is dense so we can't form it, we need  $S^{-1}$ .

Physics-based commutator: anisotropic pressure diffusion

$$\mathbf{v}^T A(\mathbf{w}) \mathbf{u} \sim \int (D\mathbf{v})^T [\eta \mathbf{1} + \eta' D\mathbf{w} \otimes D\mathbf{w}] D\mathbf{u}$$

- ▶ We would like to find an operator  $A_p$  such that

$$-S = BA^{-1}B^T \approx BB^T A_p^{-1} =: P_S$$

so that

$$P_S^{-1} = A_p (BB^T)^{-1}$$

- ▶ Note

$$BB^T \sim (-\nabla \cdot) \nabla = -\Delta$$

corresponds to a Laplacian in the pressure space (multigrid).

- ▶ If  $\eta', \nabla \eta \ll 1$  then  $A_p \sim -\eta \Delta$  so  $P_S^{-1} = \eta \mathbf{1}$



## Least squares commutator

- ▶ Schur complement

$$S = -BA^{-1}B^T$$

Suppose  $B$  is square and nonsingular. Then

$$S^{-1} = -B^{-T}AB^{-1}.$$

$B$  is not square, replace  $B^{-1}$  with Moore-Penrose pseudoinverse

$$B^\dagger = B^T(BB^T)^{-1}, \quad (B^T)^\dagger = (BB^T)^{-1}B.$$

Then

$$P_S^{-1} = -(BB^T)^{-1}BAB^T(BB^T)^{-1}.$$

- ▶ Requires 2 Poisson preconditioners for  $(BB^T)^{-1}$  per iteration
- ▶ Better with scaling, from mass matrices and effective viscosity (Elman et al. 2006, May & Moresi 2008)